

RSFIBER iPhone® iOS 10 Settings for RS Fiber Email

iPhone® Settings for RS Fiber Email Instructions:

How to set up your iPhone® for RS Fiber Email

1. Press the **Home** button on your iPhone® to access the Home screen.
2. Tap the **Settings** icon.
3. Tap **Mail**.
4. Tap **Accounts**.
5. Tap **Add Account**.
6. Tap **Other**.
7. Tap **Add Mail Account**.
8. Enter the following values for your new account: (Fig.1)
 - Name: **your full name** (as you would like it to appear on outgoing messages)
 - Email: **your@rsfiber.net** (email address)
 - Password: **your password**
 - Description: (The default is **Rsfiber** but you can label this account anything you wish.)
9. Tap **Next** in the upper-right corner of the screen.
10. On the next screen, **IMAP** should be selected by default. Scroll down and enter the following values for your **Incoming Mail Server**: (Fig.2)
 - Host Name: **email.rsfiber.net**
 - User Name: **username@rsfiber.net** (your entire email address)
 - Password: (This field is pre-populated with your RS Fiber password from step 7.)
11. Scroll down and enter the following values for your **Outgoing Mail Server**:
 - Host Name: **email.rsfiber.net**
 - User Name: **username@rsfiber.net** (your entire email address)
 - Password: **your password**
12. Tap **Next**.
13. When Mail has finished verifying your account settings, tap **Save**. You will return to the **Mail, Contacts, Calendars** configuration screen.
14. Tap **your new account**.
15. Tap **Account**.
16. Scroll down to **Outgoing Mail Server** and tap **SMTP**. (Fig.3)
17. Tap the entry for **email.rsfiber.net** and verify the following settings:
 - Use SSL: **ON**
 - Server Port: **993**
18. Tap **Done** and then tap **Account**.





Fig. 1



Incoming/Outgoing Mail Server Information Fig. 2




Fig. 3

How to set up your iPhone® for RS Fiber Email, Continued

19. Scroll down to **Outgoing Mail Server** and tap **Advanced**.
20. Scroll down and verify the following **Incoming Settings**: (Fig. 4)
 - Use SSL: **ON**
 - Authentication: **Password**
 - Server Port: **993**
21. You can also choose to store special folders on the IMAP server using the mailbox behaviors settings on this screen.
22. Tap **Account** and then tap **Done**.




Fig. 4

Need help? Visit our support page at rsfiber.coop/support or contact Technical Support at (800) 628-1754.